

System methods

3 = IPC_M_CONNECT_TO_ME
 4 = IPC_M_CONNECT_ME_TO
 5 = IPC_M_PHONE_HUNGUP
 6 = IPC_M_SHARE_OUT
 7 = IPC_M_SHARE_IN
 8 = IPC_M_DATA_WRITE
 9 = IPC_M_DATA_READ
 10 = IPC_M_DEBUG_ALL
 511 = IPC_M_LAST_SYSTEM
 512 = IPC_M_PING
 1024 = IPC_FIRST_USER_METHOD

VFS (init:vfs)

In requests

1024 = VFS_IN_OPEN
 1025 = VFS_IN_OPEN_NODE
 1026 = VFS_IN_READ
 1027 = VFS_IN_WRITE
 1028 = VFS_IN_SEEK
 1029 = VFS_IN_TRUNCATE
 1030 = VFS_IN_FSTAT
 1031 = VFS_IN_CLOSE
 1032 = VFS_IN_MOUNT
 1033 = VFS_IN_UNMOUNT
 1034 = VFS_IN_SYNC
 1035 = VFS_IN_REGISTER
 1036 = VFS_IN_MKDIR
 1037 = VFS_IN_UNLINK
 1038 = VFS_IN_RENAME
 1039 = VFS_IN_STAT
 1040 = VFS_IN_DUP

Out requests

1024 = VFS_OUT_OPEN_NODE
 1025 = VFS_OUT_READ
 1026 = VFS_OUT_WRITE
 1027 = VFS_OUT_TRUNCATE
 1028 = VFS_OUT_CLOSE
 1029 = VFS_OUT_MOUNT
 1030 = VFS_OUT_MOUNTED
 1031 = VFS_OUT_UNMOUNT
 1032 = VFS_OUT_UNMOUNTED
 1033 = VFS_OUT_SYNC
 1034 = VFS_OUT_STAT
 1035 = VFS_OUT_LOOKUP
 1036 = VFS_OUT_DESTROY
 1037 = VFS_OUT_LAST

Device manager (devman)

Devman to driver

1024 = DRIVER_ADD_DEVICE

Driver to devman

1024 = DEVMAN_DRIVER_REGISTER
 1025 = DEVMAN_ADD_CHILD_DEVICE
 1026 = DEVMAN_ADD_MATCH_ID
 1027 = DEVMAN_ADD_DEVICE_TO_CLASS

Drivers

Driver interfaces

1 = DEVMAN_DRIVER
 2 = DEVMAN_CLIENT
 3 = DEVMAN_CONNECT_TO_DEVICE
 4 = DEVMAN_CONNECT_FROM_DEVMAN
 5 = DEVMAN_CONNECT_TO_PARENTS_DEVICE

Device mapper (init:devmap)

1024 = DEVMAN_DRIVER_REGISTER
 1025 = DEVMAN_DRIVER_UNREGISTER
 1026 = DEVMAN_DEVICE_REGISTER
 1027 = DEVMAN_DEVICE_UNREGISTER
 1028 = DEVMAN_DEVICE_GET_HANDLE
 1029 = DEVMAN_NAMESPACE_GET_HANDLE
 1030 = DEVMAN_HANDLE_PROBE
 1031 = DEVMAN_NULL_CREATE
 1032 = DEVMAN_NULL_DESTROY
 1033 = DEVMAN_GET_NAMESPACE_COUNT
 1034 = DEVMAN_GET_DEVICE_COUNT
 1035 = DEVMAN_GET_NAMESPACES
 1036 = DEVMAN_GET_DEVICES

Devmap interfaces

1 = DEVMAN_DRIVER
 2 = DEVMAN_CLIENT
 3 = DEVMAN_CONNECT_TO_DEVICE

Naming service (init:ns)

1024 = NS_PING
 1025 = NS_TASK_WAIT
 1026 = NS_ID_INTRO
 1027 = NS_RETVAL

Task loader

1024 = LOADER_HELLO
 1025 = LOADER_GET_TASKID
 1026 = LOADER_SET_CWD
 1027 = LOADER_SET_PATHNAME
 1028 = LOADER_SET_ARGS
 1029 = LOADER_SET_FILES
 1030 = LOADER_LOAD
 1031 = LOADER_RUN

Userspace console

1037 = CONSOLE_GET_SIZE
 1038 = CONSOLE_GET_COLOR_CAP
 1039 = CONSOLE_GET_EVENT
 1040 = CONSOLE_GET_POS
 1041 = CONSOLE_GOTO
 1042 = CONSOLE_CLEAR
 1043 = CONSOLE_SET_STYLE
 1044 = CONSOLE_SET_COLOR
 1045 = CONSOLE_SET_RGB_COLOR
 1046 = CONSOLE_CURSOR_VISIBILITY
 1047 = CONSOLE_KCON_ENABLE